

# ON-BOARDING TOOL USER GUIDE

HKEX Orion Market Data Platform Securities Market & Index Datafeed Products Mainland Market Data Hub (MMDH)

# **DOCUMENT HISTORY**

### **Distribution Version**

Version	Date of Issue	Comments
V1.0	23 Nov 2012	First Distribution Issue
V1.1	27 May 2013	Revised library setup
V1.2	8 Mar 2016	Include VCM & CAS canned data set
V1.3	29 Jan 2019	Include the new set of test data for Reference Data Enhancement
V1.4	17 Jul 2019	Revised library setup and OS requirements Support new password policy

# CONTENTS

1	Introduction	4
1.1	OMD On-Boarding Tool Components	4
2	System Requirement, Installation, and Configuration	5
2.1	Hardware Requirements	5
2.2	Software Requirements	5
2.3	Network Requirements	5
2.4	Installation Procedures	5
2.5	Configuration	7
2.5.1	Sample Configuration	7
2.5.2	Configuration Description	8
3	System Functions	10
3.1	Scope	10
3.1.1	Unsupported functions	
3.1.2	System Functions	
3.1.3	System Relationship Diagram	
3.2	Logon request	
3.3	Change Password Request	
3.4	Functional Test Simulation	
3.5	Workload Test Simulation	
3.6	Reporting and Logging	
3.6.1	MMDH Simulator Report	
3.6.2	Log File	
4	Operational Procedures	
4.1	Starting OMD On-Boarding Tool	
4.2	Log Files	15
4.3	Test Result Verification	
4.3.1	Functional Test Simulation	
4.3.2	Workload Test Simulation	
4.3.3	Result Checking for System Readiness	
Appendi		
A.1	MMDH On-Boarding Tool cannot be installed	
A.2	MMDH On-Boarding Tool cannot be started	
A.3	Cannot open config file	
A.4	Cannot open canned data	
A.5	Server 127.0.0.1:17000 Error: Connection refused	
A.6	Server 127.0.0.1:17000 Error: Connection reset by peer	17
A.7	LogonResponse: 5 (Invalid username or password)	17
A.8	LogonResponse: 3 (New session password does not comply with policy)	17
Appendi	x B MMDH Logon Encryption Sample	

#### 1 Introduction

MMDH On-Boarding Tool is a simulation tool that provides testing facilities with simulated market data for the MMDH Information Vendors and End-users (Clients). MMDH On-Boarding Tool facilitates the development, enhancement and testing of the Clients' application systems which receive and process data from MMDH. As HKEX implements changes to MMDH from time to time to support its business initiatives, MMDH On-Boarding Tool will help Clients ensure their readiness for the implementation before joining the Client Test or Market Rehearsal (MR) as required by HKEX.

MMDH On-Boarding Tool also facilitates Clients' workload test (e.g. capacity and performance tests) with the built-in throttle control mechanism. Clients can also make use of the On-Boarding Tool for the testing of their own system development / enhancement. By distributing different test datasets (test data files) to the Clients, HKEX can support clients in testing their systems' readiness for various implementations of MMDH initiatives.

Table 1 Acronyms used in this document

AES	Advanced Encryption Standard
CFB	Cipher FeedBack
DH	Diffie-Hellman
HKEX	Hong Kong Exchanges and Clearing Limited
IV	Information Vendor
MMDH	Mainland Market Data Hub
OMD	Orion Market Data Platform
SHA	Secure Hash Algorithm

#### 1.1 OMD On-Boarding Tool Components

Component	Description
MMDH On- Boarding Tool	MMDH On-Boarding Tool reads canned data and sends messages to Client's application system
MMDH testing client	MMDH testing client application is used to verify the MMDH On-Boarding Tool setup and if it runs properly
Canned Data	<ul> <li>Fictitious trading data to facilitate testing</li> <li>Separate files may exist for different testing purpose (e.g. workload test or functional test)</li> <li>MMDH On-Boarding Tool will read the canned data and send respective messages to Client's application system.</li> </ul>

## 2 System Requirement, Installation, and Configuration

#### 2.1 Hardware Requirements

- 64-bit AMD or Intel processor
- 4 GB RAM
- 20 GB available disk space

#### 2.2 Software Requirements

HKEX will not provide the follow software / libraries. Clients should go to official website and download software / libraries

- Red Hat Enterprise Linux (RHEL) 7.4 64-bit Edition, or CentOS 7.4 64-bit
- Boost C++ Libraries (Recommended Version: 1.53.0)
- Xerces-C++ (Recommended Version: 3.1.1)
- Crypto++ (Recommended Version: 5.6.2)

#### 2.3 Network Requirements

- Mode of transmission IP-based Network
- Communication Line Speed LAN is preferred with bandwidth greater than the configured Workload rate. e.g. 10Mbps or above is recommended.
- Communication Protocol TCP

#### 2.4 Installation Procedures

Ste	Description
р	
1.	Install Boost C++ Libraries
	<pre>tar xvfz boost_1_53_0.tar.gz cd boost_1_53_0 ./bootstrap.sh ./b2</pre>
	Modify ~/.bashrc to include the following
	export LD_LIBRARY_PATH=\$LD_LIBRARY_PATH:/home/user/Development/include/boost_1_4 53_0/stage/lib
	source ~/.bashrc
2.	<pre>tar xvf xerces-c-3.1.1-x86_64-linux-gcc-3.4.tar.gz</pre>
	Modify ~/.bashrc to include the following
	<pre>export LD_LIBRARY_PATH=\$LD_LIBRARY_PATH:/home/user/Development/inc lude/xerces-c-3.1.1-x86_64-linux-gcc-3.4/lib</pre>
	source ~/.bashrc

```
3.
     Install Crypto++
     unzip cryptopp562.zip -d cryptopp562
     cd cryptopp562
     Modify GNUmakefile
     Uncomment the following
      # CXXFLAGS += -fPIC
     make
     make libcryptopp.so
     make install PREFIX=/home/user/Development/include/cryptopp
     Modify ~/.bashrc to include the following
             export
             LD LIBRARY PATH=$LD LIBRARY PATH:/home/user/Development/include/cryptopp/li
     source ~/.bashrc
4.
     If you are installing from a disc (e.g. CD or DVD), you need to create a mount point and mount
     the file system. For example,
     mkdir /media/OMD
     mount -t udf /dev/sr0 /media/OMD
5.
     Copy the 'mmdh onboardingTools 1.4.tar.gz' directory from the provided media to the desired
     host. For example,
     cp -r /media/OMD/mmdh onboardingTools 1.4.tar.gz /home/userid
6.
     Extract the TAR/GZIP file to the correct directory
     tar xvzf mmdh onboardingTools 1.4.tar.gz -C /opt
     *Note* - the tool will not work if they are not in the correct directory structure.
7.
     Add the correct directory permissions
     chown -R {userid:usergroup} /opt/HKEX
     Where userid & usergroup are system account that using to run the onboarding tool.
     To verify the installation was successful, the following command will show the contents of the
8.
     install directory
     ls /opt/HKEX/omd/mmdh/
     If successful, the directory will contain
     bin config data lib log
     If you are installing from a disc, unmount the file system and remove the mount point. For
     example,
     umount /dev/sr0
      rmdir /media/OMD
```

#### 2.5 Configuration

Configuration is at "/opt/HKEX/omd/mmdh/config/MMDH.xml".

#### 2.5.1 Sample Configuration

The following shows the content of a sample configuration file.

```
<?xml version="1.0" encoding="utf-8" standalone="no" ?>
<MMDH>
 <Address>127.0.0.1</Address>
 <Port>17000</Port>
 <UserName>omd-client1</UserName>
 <PasswordPolicy>
   <!-- MinLength in number of characters -->
   <MinLength>16</MinLength>
   <!-- 0 = Password may contain uppercase character A to Z -->
   <!--1 = Password must contain uppercase character A to Z -->
   <ContainUpper>1</ContainUpper>
   <!-- 0 = Password may contain uppercase character a to z -->
   <!--1 = Password must contain lowercase character a to z-->
   <ContainLower>1</ContainLower>
   <!-- 0 = Password may contain digit -->
   <!--1 = Password must contain digit 0 to 9 -->
   <ContainDigit>1</ContainDigit>
   <!-- 0 = Password may contain special character -->
   <!-- 1 = Password must contain special characters -->
   <ContainSpecial>1</ContainSpecial>
   <!-- Special characters set must be included in the password -->
   <SpecialCharSet>!@#$^&amp;*()</specialCharSet>
   <!-- Password must be different from last N passwords -->
   <DiffFromLast>5</DiffFromLast>
 </PasswordPolicy>
 <!-- Most recent password is at top of Passwords list -->
   <Password>Aa!000000000000
   <Password>Aa@1111111111111
   <Password>Aa#222222222222
    <Password>Aa$33333333333
   <Password>Aa^44444444444
 </Passwords>
 <!-- ThrottleRate in messages per second -->
 <ThrottleRate>1000</ThrottleRate>
 <!-- ThrottleInterval in ms -->
 <ThrottleInterval>10</ThrottleInterval>
 <CannedDataPath>/opt/onboardingtool/data/p1-
canned.dat</CannedDataPath>
 <Log>
```

```
<!--
                                   /* system is unusable */
       SEV_EMERGENCY = 0
SEV_ALERT = 1
                                   /* action must be taken
immediately */
       SEV_CRITICAL
                        = 2
= 3
= 4
= 5
                                    /* critical conditions */
                                    /* error conditions */
       SEV_ERROR
       SEV_ENTING
SEV_WARNING
                                   /* warning conditions */
       SEV_NOTICE
                                   /* normal but significant
condition \overline{*}/
      SEV_INFORMATIONAL = 6 /* informational */
SEV_DEBUG = 7 /* debug-level messages */
      -->
    <SeverityCeiling>
      <File>7</File>
      <Console>3</Console>
      <Syslog>3</Syslog>
    </SeverityCeiling>
    <Path>../log</Path>
    <!-- 0 = Disable outgoing message, 1 = Enable outgoing message --
    <EnableOutgoingMsg>1</EnableOutgoingMsg>
  <ReportPath>/opt/onboardingtool/report</ReportPath>
```

#### 2.5.2 Configuration Description (MMDH.xml)

Configuration	Description
<address></address>	The MMDH On-Boarding ToolIP address for the Client's application system to connect to
<port></port>	The MMDH On-Boarding Toolport number for the Client's application system to connect to
<username></username>	Used in the Logon (1101) message Username field
<passwordpolicy></passwordpolicy>	Password policy related configuration
<minlength></minlength>	Minimum number of character required for a valid password
<containupper></containupper>	Whether password is required to contain uppercase character A to Z
<containlower></containlower>	Whether password is required to contain lowercase character a to z
<containdigit></containdigit>	Whether password is required to contain digit 0 to 9
<containspecial></containspecial>	Whether password is required to contain special character
<specialcharset></specialcharset>	The special character set
<difffromlast></difffromlast>	Password is different from the last N password, where N is specified using this parameter.
<passwords></passwords>	List of current and previously used passwords
<password></password>	The first entry is the current password.
<throttlerate></throttlerate>	The number of messages to send out in a second
<throttleinterval></throttleinterval>	The number of milliseconds between start sending out two batches of messages
<canneddatapath></canneddatapath>	The full path and file name for canned data
<log></log>	Logging related configuration
<severityceiling></severityceiling>	The largest severity level that will be logged
<file></file>	The largest severity level that will be logged to file
<console></console>	The largest severity level that will be logged to console

	<syslog></syslog>	The largest severity level that will be logged to syslog
	<path></path>	Log file path
	<enableoutgoingmsg></enableoutgoingmsg>	Enable outgoing message logging. When this option is enabled, outgoing messages will be logged to YYYYMMDD-HHMMSS-MmdhServer.log
<reportpath></reportpath>		Path to save report to

#### 3 System Functions

#### 3.1 Scope

MMDH On-Boarding Tool provides securities market data simulation and workload testing facilities to Clients. The system functions and the relationship diagram between MMDH On-Boarding Tool and Clients' application systems are listed below.

#### 3.1.1 Unsupported functions

Only the following password policies are checked.

- Password shall contain at least 16 characters
- Password shall contain a combination of letters (both upper & lower case), numbers (0-9) and special characters (!@#\$^&\*())
- New password shall not be the same as any of the last 5 passwords

The following messages are not supported in the On-Boarding Tool.

Message	Message Type
Logout	1103
Refresh Request	1201
Refresh Response	1202
Refresh Complete	203

For Logon Response (1102), only the following SessionStatus values are handled.

SessionStatus	Description
0	Session active
1	Session password changed
3	New session password does not comply with policy
5	Invalid username or password
104	Already Connected

#### 3.1.2 System Functions

- Logon Request
- Change Password Request
- Functional Test Simulation
- Workload Test Simulation
- Reporting and Logging

Details will be provided in subsequent sections 3.2 to 3.6.

Function	Description
Logon Request	Handles logon request from Client's application system following the same mechanism as production MMDH except that it does not support intra-day recovery. (i.e. InternalSeqNum in Logon Request will be ignored). It will authenticate the username / password sent by MMDH Client's application system.
Change Password Request	Handles change password request from Client's application system following the same mechanism as production MMDH. It will check against the password history and reject a new password if it is the same as any of the last N passwords, where N is a configurable parameter.

Functional Test Simulation	Plays back simulated market data to assist Clients in conducting their functional test, either to prepare for implementation of the HKEX initiatives, or for their own application system enhancement.
Workload test Simulation	Plays back simulated market data to assist Clients in conducting their workload test, either to prepare for message volume upgrade initiated by HKEX, or for their performance and capacity test for their application system.
Reporting and Logging	Offers "MMDH On-Boarding Tool Workload Report" to Clients to verify their workload test result  Offers "Log file" to Clients for their verification of the functional test result or for troubleshooting.

#### 3.1.3 System Relationship Diagram

Clients use captured data for their internal testing



#### 3.2 Logon request

The following is a list of steps to logon to MMDH On-Boarding Tool.

- 1. MMDH Client's application system initiates connection request.
- 2. MMDH On-Boarding Tool accepts connection request.
- 3. MMDH On-Boarding Tool sends Send Key message to MMDH Client's application system .
- 4. MMDH Client's application system sends logon message to On-Boarding Tool.
- 5. If authentication is successful, the On-Boarding Tool sends logon response with SessionStatus equal to 0 (Session Active) followed by market data messages. Otherwise, it sends logon response with SessionStatus equal to 5 (Invalid username or password).

Please refer to MMDH interface specification section 3.4.1. The password will be encrypted using the following.

- 1. OMD public key field and Client's application system's private key, both generated using the same set of Diffie-Hellman (DH) parameters (prime, generator, subgroup order)
- 2. Initialization Vector in the Send Key message provided by MMDH On-Boarding Tool

The AES CFB mode is used for encryption and decryption

Please refer to Appendix B for MMDH Logon Encryption Sample.

#### 3.3 Change Password Request

 Client's application can change the password by specifying EncryptedNewPasswordLen and EncryptedNewPassword

fields within the Logon (1101) message. MMDH On-Boarding Tool simulates MMDH to handle change password request and sends back corresponding response message to Client's application systems. (Please refer to MMDH interface specification sections 3.4.2 and 3.4.3 for details.)

#### 3.4 Functional Test Simulation

After successful logon, MMDH On-Boarding Tool will use the configuration in MMDH.xml to playback the desired simulated market dataset according to the workload rate.

HKEX will provide different simulated market datasets for different testing purposes. Clients can load the appropriate dataset to MMDH On-Boarding Tool and start playing back for their functional test on their own MMDH application systems.

MMDH On-Boarding Tool can store and use multiple test data files. Clients are recommended to store all test files in /opt/HKEX/omd/mmdh/data and input the correct test file before the test session starts.

#### 3.5 Workload Test Simulation

Simulated market data playback is intended to assist Clients in conducting their workload test. Workload test prepares Clients for HKEX initiated message volume upgrade, and for their application system's performance and capacity test. The <ThrottleRate> and <ThrottleInterval> parameters in the MMDH On-Boarding Tool configuration file (MMDH.xml) control market data feed workload.

#### 3.6 Reporting and Logging

MMDH On-Boarding Tool provides "MMDH On-Boarding Tool Workload Report" to Clients to verify their workload test result. Each test session generates the report and puts the report in a folder defined by <ReportPath> parameter in the MMDH On-Boarding Tool configuration file (MMDH.xml). Please refer to section 0 for details.

MMDH On-Boarding Tool provides "Log file" to Clients for checking against their application system receiving log. It helps Clients to verify their application's functionalities and correctness. The "Log file" also facilitates their verification of the functional test result and for their troubleshooting.

#### 3.6.1 MMDH On-Boarding Tool Workload Report

The test report name is in the format of YYYYMMDD-HHMMSS-Report.log. It shows the workload rate and delay information throughout the whole test session. It is a text file and the sample report layout is shown as below.

Report Field	Description
Time	The per minute statistics sampling interval in HH:MM format
Workload Rate	The market data message dissemination rate in messages per second
	for the statistics sampling interval

Max Delay	Delay is defined as the time difference between the time when MMDH On-Boarding Tool is ready in sending the market data message and the time when MMDH On-Boarding Tool sends the same market data message to the Client.
	Max Delay for a statistics sampling interval is the largest delay for all messages sent out within the statistics sampling interval.
Mean Delay	Mean Delay for a statistics sampling interval is the average delay for all messages sent out within the statistics sampling interval.

```
Date: 2012-10-22
Configured Workload Rate: 10000 messages per second (msg/s)

Time Workload Rate (msg/s) Max Delay (s) Mean Delay (s)
11:13 9994.806485 0.007856 0.002018

Average of [Workload Rate (msg/s)] = 9994.806485

Maximum of [Max Delay (s)] = 0.007856

Average of [Mean Delay (s)] = 0.002018
```

#### 3.6.2 Log File

The log file name is in the format of YYYYMMDD-HHMMSS-MmdhServer.log. It contains messages received by MMDH On-Boarding Tool (incoming) and messages sent out by MMDH On-Boarding Tool (outgoing). It is a text file and the sample report layout is shown as below.

Field	Description
Process ID	Is always MmdhServer
Thread ID	Different threads have different thread IDs
Date time	The local date and time at which the message was logged
Severity	The severity level of the log message
Entry	Incoming messages have "[Incoming]" prefix Outgoing messages have "[Outgoing]" prefix

#### Sample Log

[MmdhServer.140030807193376, Oct 22 14:14:23.165; Notice]: Logon Configuration: In the above sample, we have

Field	Value
Process ID	MmdhServer
Thread ID	140030807193376
Date time	Oct 22 14:14:23.165
Severity	Notice
Entry	Logon Configuration:

# 4 Operational Procedures

# 4.1 Starting OMD On-Boarding Tool

Step	Description												
1.	Run the MMDH On-Boarding Tool												
	cd /opt/HKEX/omd/mmdh/bin												
_	./MmdhServer -c/config/MMDH.xml												
2.	You will see the following message.												
	Please enter throttle rate (ENTER = 10000 messages per second)												
3.	Do one of the following												
Э.	55 one of the following												
	Press the Enter key to accept default throttle rate												
	2. Input another throttle rate and press the Enter key to use the new rate  Output  Description:												
4.	The selected throttle rate similar to the following will be shown.												
	,												
	Throttle rate is 10000 messages per second.												
5.	You will see the following message.												
	Please enter canned data path (ENTER =												
_	/opt/HKEX/omd/mmdh/data/mmdh_canned_data_02102012.cap)												
6.	Do one of the following												
	Press the Enter key to accept default canned data path												
	Input another canned data path and press the Enter key to use the new path												
7.	The selected canned data path similar to the following will be shown.												
	6 m a control of the												
	Canned data path is												
	/opt/HKEX/omd/mmdh/data/mmdh_canned_data_02102012.cap												
8.	You will see the following header showing the current date.												
	Date: 2012-10-18												
	Configured Workload Rate: 10000 messages per second (msg/s)												
	Time Workload Rate (msg/s) Max Delay (s) Mean Delay (s)												
9.	Time Workload Rate (msg/s) Max Delay (s) Mean Delay (s) Client's Application system connect to MMDH On-Boarding Tool												
9.	Client's Application system connect to MiMDH On-Boarding Tool												
10.	You will see something similar to the following at the MMDH On-Boarding Tool terminal. The												
10.	output will be updated every 5 seconds before completion.												
	output iiiii se apaatea every s seconas serore completionii												
	16:09:50 9796.695877 0.004535 0.001633												
	16:09:55 10012.334631 0.008353 0.001383												
	16:10:00 9992.793737 0.007968 0.001363												
	16:10:05 9964.659816 0.004953 0.001237												
	Average of [Workload Rate (msg/s)] = 9996.656777												
	Maximum of [Max Delay (s)] $= 0.008353$												
	Average of [Mean Delay (s)] = 0.001359												

11. You will see something similar to the following in the report. The report will be updated every minute before completion.

Date: 2012-10-18
Configured Workload Rate: 10000 messages per second (msg/s)

Time Workload Rate (msg/s) Max Delay (s) Mean Delay (s)
16:09 10008.867897 0.008353 0.001387
16:10 9986.874052 0.007968 0.001337

Average of [Workload Rate (msg/s)] = 9996.656777
Maximum of [Max Delay (s)] = 0.008353
Average of [Mean Delay (s)] = 0.001359

Verify MMDH On-Boarding Tool setup and run properly using MMDH testing client

Step	Description											
1.	Run the MMDH testing client in another terminal											
	<pre>cd /opt/HKEX/omd/mmdh/bin ./MmdhClient -c/config/MMDH.xml</pre>											
2.	You will see the following message.											
	Please enter a password (maximum 20 characters)											
3.	Input the password and press the Enter key											
4.	You will see the following message.											
	Please enter a new password (maximum 20 characters, ENTER = none)											
5.	Do one of the following											
	<ol> <li>Press the Enter key if you are not changing password</li> <li>Input the new password to change to and press the Enter key</li> </ol>											
6.	You will see the following message at the testing client terminal.											
	LogonResponse: 0 (Session active)											

#### 4.2 Log Files

There are three types of log files in the MMDH On-boarding Tool and they are described as follows.

Log file	Description
YYYYMMDD-HHMMSS- MmdhClient.log	Contains MmdhClient log messages
YYYYMMDD-HHMMSS- MmdhServer.log	Contains MmdhServer log messages
YYYYMMDD-HHMMSS- Report.log	Contains a report that shows per minute and overall workload rate, max delay, and mean delay

Log files can be found at the log file path.

#### 4.3 Test Result Verification

#### 4.3.1 Functional Test Simulation

Clients can check if the following criteria are met to verify if their systems are functional ready for subsequent HKEX on-boarding activities.

- No error generated during the test session
- All outgoing messages logged in the MmdhServer log file, e.g. YYYYMMDD-HHMMSS-MmdhServer.log have been received by Client's application system. The messages can be verified by matching the Sequence Number (SeqNum) in this sent log file.

#### 4.3.2 Workload Test Simulation

Clients can check if the following criterion is met to verify if their systems can handle MMDH planned capacity for participating in subsequent HKEX on-boarding activities.

• No error generated during the test session

#### 4.3.3 Result Checking for System Readiness

HKEX may request clients to submit functional and/or workload test simulation test results with the corresponding log/report. This confirms that their systems are ready for HKEX major business initiative implemented in MMDH, for joining HKEX arranged Readiness Test, Client Tests and Market Rehearsals.

## **Appendix A Troubleshooting**

#### A.1 MMDH On-Boarding Tool cannot be installed

Please make sure the target installation machine meet the system requirement stated in section 2 and root privilege is required during installation.

#### A.2 MMDH On-Boarding Tool cannot be started

Please make sure the target installation machine meet the system requirement stated in section 2 and:

- Required LAN connection is enabled
- Required port number (stated in <Port> parameter in MMDH.xml) is not used by other software
  or blocked by any security software such as firewall.

#### A.3 Cannot open config file

Make sure that MMDH.xml exists and in the correct location

#### A.4 Cannot open canned data

Make sure that canned data file exists and in the correct location

#### A.5 Server 127.0.0.1:17000 Error: Connection refused

Make sure that MmdhServer is started before MmdhClient

#### A.6 Server 127.0.0.1:17000 Error: Connection reset by peer

Check if MmdhServer is still running

## A.7 LogonResponse: 5 (Invalid username or password)

Check MMDH.xml to make sure that you have entered the correct password

#### A.8 LogonResponse: 3 (New session password does not comply with policy)

Check MMDH.xml to make sure that the new password complies with password policy

# **Appendix B MMDH Logon Encryption Sample**

An example shows how to logon to MMDH.

```
switch (msgType) {
  case SEND_KEY_TYPE:
  // Make use of Prime, Generator, PrimeOrderSubgroup, and OMDPublicKey fields
  // in Send Key message
  processSendKeyMsg();
   // Generate Diffie-Hellman public and private keys
   generateKeyPair();
   // Create shared key using generated private key and received OMDPublicKey field
   computeSharedKey();
   // Calculate SHA-256 message digest
   calcDigest();
   // Use AES to encrypt password
   aesEncrypt(password, passwordLen, encryptedPassword);
   // If change password, use AES to encrypt new password
   aesEncrypt(newPassword, newPasswordLen, encryptedNewPassword);
   break;
 }
 case LOGON_RESPONSE_TYPE:
   processLogonResponseMsg();
   break;
 default:
   break;
```

Clients can follow above pseudo code to compose Logon message. The following shows Send Key message sample field values. Clients can derive the encrypted password as per illustration.

Field	Valu	ıe														
MsgSize	532	2														
MsgType	110	)5														
Prime	b1 52 60 13 ac 4e a1 e6	0b c9 73 ec cb ff 51 8c	8f 9f e2 b4 dd d6 af fd	96 bc 86 ae 7d fa 5f a7		80 06 a2 06 c4 64 c8 4d	e0 a3 3d 11 bd 47 b4 a7	1d c6 18 23 70 38 bd 08	de 9a 98 24 98 fa 45 df	92 6a 38 97 48 a3 bf 1f	de 9d ef 5c 8e 1a 37 b2	1e	ae 52 2e d4 21 f5 36 2e	5d d2 e6 9b 9a 5b 5c 4a	54 3b 52 83 73 cc 1a 43	ec 61 c0 bf 72 c0 65
Generator	a4 f8 26 16 d7 a6 d6 85	d1 10 6f 02 fb a2 62 8f	cb 4d ea 17 d7 4c a4 4d	d5 d2 1e b4 d3 08 d1 ce	c3 58 5c b0 b9 7a 8e f9	fd ac 41 1b a9 09 73 7c	34 50 56 88 2e 1f af 2a	12 7f 4b 6a e1 53 a3 24	67 d6 77 5e 90 1d 2d 85	65 40 7e 91 9d bf 77 5e	a4 6c 69 54 0d 0a 9d 6e	42 ff 0f 7f 22 01 59 eb	ef 14 55 9e 63 69 18 22	b9 26 04 27 f8 b6 d0 b3	99 6d f2 49 0a a2 8b b2	05 31 13 f4 76 8a c8 e5
PrimeOrderSubgroup	00 00 00 00 00 00 00 81	00 00 00 00 00 00 00 a8	00 00 00 00 00 00 00 df	00 00 00 00 00 00 00 27	00 00 00 00 00 00 00 8a	00 00 00 00 00 00 00 ba	00 00 00 00 00 00 00 4e	00 00 00 00 00 00 00 7d	00 00 00 00 00 00 00 64	00 00 00 00 00 00 00 b7	00 00 00 00 00 00 00	00 00 00 00 00 00 00 9d	00 00 00 00 00 00 f5 49	00 00 00 00 00 00 18 46	00 00 00 00 00 00 aa 23	00 00 00 00 00 00 00 87 53
OMDPublicKey	10 8b 9d cc a7 5f ac 46 e7	f3 17 6c c7 e1 08 a2 fc da	54 06 78 2b d4 a4 82 72 0c	8b 5f 30 26 21 97 b9 ba 79	ba 47 53 ba bc 58 0a 75 bc	42 8a 78 60 f5 76 a0 19	5d 8e d9 16 be 09 75 c2 8d	99 47 f4 eb 8e b2 bf 08 95	80 7b 90 fe f3 ae 7e 86 54	0d 6b 20 cc 7f de 26 9b 1d	1a 5c 2a da 60 d0 45 56 b1	ae 1b 87 84	89 3c a5 cc 5b 9b 7e ba c8	07 60 9b c0 ec 2d 7b e2 55	ae ac 52 c1 03 4e eb 32 68	75 ea 47 9a 2f 42 3d c5 c5

The following shows Logon message field values using Client Public Key derived from the information provided in above SendKey message and the Client Private Key.

Field	Valu	ıe														
MsgSize	190															
MsgType	1101															
Username	omd-client1															
InternalSeqNum	0															
ClientPublicKey	00 90 d5 eb a5 cb	9e de fc 6d de 52	d5 c4 9c 23 ed 2b	99 5f aa 06 44 7a	3d 06 b3 d6 52 2c	3d 98 0d 85 37 d2	c8 77 f4 57 3e f6	ae 33 97 54 38 fb	a2 83 9a 30 28 04	d2 db 6a 8e 45 9a	ea a1 f9 37 55 7c	c1 29 50 db f9 f4	8b 6f 72 23 56 07	dd 89 b8 cc 56 c2 6f a8	1d e9 59 af d7 50	e5 1e 71 c1 15

ClientPrivateKey			02 d5	bc fb	77	c5	b6	5c	01	61	f5	f6	d2	7f	5f	49
EncryptedPasswordLen	8															
EncryptedPassword	29	b8	34	2d	61	5d	46	14								
EncryptedNewPasswordLen	0															
EncryptedNewPassword																